

Epson R2880 Printing

PREPPING YOUR IMAGE FILES

Preparing an Image File for printing with the Epson R2880

- 1) Create a copy of your original or edited image file.
- 2) Your file should be in RGB mode (in the Image-->Mode Menu). Ideally your file would have an ProPhoto RGB profile (also in the Image-->Mode-->Convert Profile Menu)
- 3) Use Image Size (in the Image Menu) to adjust your document to the size you want to print it.
 - a) Maximum paper size is 13 inches by 19 inches for sheets of paper.
 - b) Ideal resolutions for the Epson 2200 are 360, 300, 240 and 180 dpi.
- 4) Flatten your image. The "Flatten Image" action is found at the bottom of the "Layer" Menu.
- 5) Save your file.

PRINTING YOUR IMAGES

Once you have prepared the image file for printing, use the following instructions to print the image file. You will be navigating three separate windows during the printing process.

Print Window - (Adobe)

- 1) From the File Menu choose "Print"
- 2) The "Print" window appears. Choose "Page Setup..."

Page Setup Window

- 3) The "Page Setup" window appears.
 - a) Click on the "Format for:" pop-up button. Choose "Epson R2880".
 - b) Click on the "Paper Size:" pop-up button. Choose a paper size that matches your paper size.
Max paper size is 13 inches by 19 inches for sheets of paper.
 - c) From the "Orientation" section, choose Portrait (image more vertical) or Landscape (image more horizontal)
 - d) Leave "Scale:" at 100%.
 - e) Click the "OK" button.
 - f) The "Page Setup" window closes and takes you back to the Print window.

Print Window - (Adobe)

- 4) Your image should now fit within the preview pane in the upper left corner of the "Print" window. If not you have chosen a paper size that is too small or an incorrect orientation. Return to the "Page Setup" window.
- 5) See Color Management handout for details on using ICC profiles.
- 6) Click the "Print..." button.

Print Window - (Apple)

- 7) The Photoshop "Print" window closes and the standard Apple "Print" window appears.
 - a) Click on the "Printer" pop-up button. Choose "Epson R2880".
 - b) Click on the "Copies and Pages" pop-up button. Choose "Print Settings".
 - i) Click the "Media Type" pop-up button. Choose your paper type.
 - ii) Click the "Advanced Settings" Mode radio button.
 - iii) Click on the "Print Quality" pop-up button. Choose your preferred resolution.
Photo - 1440 dpi is suitable for most applications.
 - iv) Uncheck the "High Speed" check box.
 - c) Click the "Print" button at the lower right hand corner of the window.

Your image should now print.